

# N960FXXU1ARH5 - SM-N960F DBT

## Germany

### Android 8.1.0

1. [SamMobile.com](http://SamMobile.com)
2. [Firmware](#)
3. [SM-N960F](#)
4. N960FXXU1ARH5
5. Download

Download the firmware for the SM-N960F with product code DBT from Germany. This firmware has version number PDA N960FXXU1ARH5 and CSC N960FOXMIARGD. The operating system of this firmware is Android 8.1.0 , with build date Tue, 07 Aug 2018 10:25:59 +0000. Security patch date is 2018-08-01, with changelist 14091311.

Model	<a href="#">SM-N960F</a>
Model name	
Country	
Version	Android 8.1.0
Changelist	14091311
Build date	Tue, 07 Aug 2018 10:25:59 +0000
Security Patch Level	2018-08-01
Product code	<a href="#">DBT</a>
PDA	N960FXXU1ARH5
CSC	N960FOXMIARGD

Approx. 15 kB/Sec

Non-Premium Members

SamMobile Premium Plans:

€14.50 = 4 weeks

€20 = half year\*

€25 = year\*

Galaxy S9+ winner month March: Username: 3051741 from Spain.

Galaxy S9+ winner month April: Username: polymorf34 from France.

Galaxy S9 winner month May: Username: DirKTDL from Belgium.

Galaxy S9 winner month June: Username: leagoomlk from Malaysia.

Galaxy S9 winner month July: Username: Tyrawr from New Zealand.

Memberships with a \* make a chance to win prizes.

\*This month(August): Samsung Galaxy Note 9.\*

[Join us now!](#)

[Premium Members only](#)

Test your speed [here](#)

Instructions (5 files)

1. [Download Odin v3.13.1](#)
2. Extract the firmware file you just downloaded. You should get 5 files:  
AP (System & Recovery)  
BL (Bootloader)  
CP (Modem / Radio)  
CSC\_\*\*\* (Country / Region / Operator)  
HOME\_CSC\_\*\*\* (Country / Region / Operator)
3. Add each file to its respective field in Odin v3.13.1. Use CSC\_\*\*\* if you want to do a clean flash or HOME\_CSC\_\*\*\* if you want to keep your apps and data.
4. Reboot your phone in Download / Odin mode (make sure your device is off) with the following button combo: POWER + VOLUME DOWN + BIXBY  
Other options in case first option did not work or isn't possible.  
Option 2 VOLUME DOWN + VOLUME UP than USB cable  
Option 3 POWER + VOLUME DOWN + VOLUME UP  
Option 4 POWER + VOLUME DOWN + HOME BUTTON  
Option 5 (Note9) USB cable + VOLUME DOWN + BIXBY
5. Once in download mode, connect your phone to the PC, preferably using the original USB cable you got with your phone. Odin should detect your device and a BLUE box will show up with the COM port number. (Be sure, the SAMSUNG-drivers are installed on your PC!)
6. Do NOT tick any extra boxes. The only options to be ticked are F.Reset Time and Auto-Reboot.
7. Click the start button, wait for Odin to say 'PASS' in a GREEN box. Once the flash is complete, your phone will reboot, and you can disconnect your phone from the PC.

#### Instructions (1 file)

1. [Download Odin v3.13.1](#)
2. Extract the firmware file you just downloaded. You should get 1 file:  
AP (System & Recovery)
3. Add each file to its respective field in Odin v3.13.1. Use CSC\_\*\*\* if you want to do a clean flash or HOME\_CSC\_\*\*\* if you want to keep your apps and data.
4. Reboot your phone in Download / Odin mode (make sure your device is off) with the following button combo: POWER + VOLUME DOWN + BIXBY  
Other options in case first option did not work or isn't possible.  
Option 2 VOLUME DOWN + VOLUME UP than USB cable  
Option 3 POWER + VOLUME DOWN + VOLUME UP  
Option 4 POWER + VOLUME DOWN + HOME BUTTON  
Option 5 (Note9) USB cable + VOLUME DOWN + BIXBY
5. Once in download mode, connect your phone to the PC, preferably using the original USB cable you got with your phone. Odin should detect your device and a BLUE box will show up with the COM port number. (Be sure, the SAMSUNG-drivers are installed on your PC!)
6. Do NOT tick any extra boxes. The only options to be ticked are F.Reset Time and Auto-

Reboot.

7. Click the start button, wait for Odin to say 'PASS' in a GREEN box. Once the flash is complete, your phone will reboot, and you can disconnect your phone from the PC.